
Software Release Notes

Christie E400 Controller Software v4.2.5

This document provides information about the Christie E400 Controller Software version 4.2.5, released to provide improved functionality.

Applies to the following products	Prepared for
<ul style="list-style-type: none">Christie E400 Controller	Internal and External Operators and Service Technicians

Resolved issues

The following items are resolved with this release:

- Resolved an issue where brightness adjustment schedules were not followed.
- Interface improvements, including updated translations.

Moving to Christie E400 Controller Software 4.2.5

When a new version of the software is released, the Christie E400 Controller Software must be upgraded.

- Uninstall the Christie E400 Controller software, version 4.3.1.
- Install Christie E400 Controller software, version 4.2.5.
- Open the software, and switch to the **Screen Connection** tab.
- Click **Read from HW**.
- Verify the array configuration is correct.

Technical Support

Technical support for Christie products is available at:

North and South America: +1-800-221-8025 or tech-support@christiedigital.com

Europe, Middle East, and Africa: +44 (0) 1189 778111 or techsupport-emea@christiedigital.com

Asia Pacific: tech-asia@christiedigital.com